


0. PVE



iso

```
=====
EPower Server SysMenu V11.1
=====

OS Install Disk: No

Hostname: eppve

DHCP
eth0 Address: 192.168.31.29
eth0 Netmask: 255.255.255.0
eth0 Gateway: 192.168.31.1
eth0 MacAddr: 00:09:da:e8:60:56

EPS Admin: https://192.168.31.29:1111
PVE Admin: https://192.168.31.29:8006
PBS Admin: https://192.168.31.29:8007

=====

i) Install To Disk
p) Ping

Press <Enter> to refresh

You Choice is:
-
```

Disk

i) Install To Disk

sda

```
=====
      EPower Server SysMenu V11.1
=====

OS Install Disk: No

Hostname: eppve

DHCP
eth0 Address: 192.168.31.29
eth0 Netmask: 255.255.255.0
eth0 Gateway: 192.168.31.1
eth0 MacAddr: 00:09:da:e8:60:56

EPS Admin: https://192.168.31.29:1111
PVE Admin: https://192.168.31.29:8006
PBS Admin: https://192.168.31.29:8007
=====

i) Install To Disk
p) Ping

Press <Enter> to refresh

You Choice is:

i

sda;105G;HARDDISK

Select install disk [ext: sda or sdb]: sda_
```

```
=====
EPower AIOT SysMenu V11.1
=====

OS Install Disk: No

Hostname: eppve

DHCP
eth0 Address:
eth0 Netmask:
eth0 Gateway:

EPS Admin: https://:1111
PVE Admin: https://:8006
PBS Admin: https://:8007

=====

2) IP Configuration
3) Changing Hostname
4) Format Disk
6) Changing root Password
7) Reboot
8) Shutdown
9) Logout

i) Install To Disk
p) Ping

Press <Enter> to refresh

You Choice is:

i

vda;105G;
vdb;105G;
vdc;105G;

Select install disk [ext: sda or sdb]: vda
Copy Wait...
-
```

OS Install Disk : YES ()

```
=====
EPower Server SysMenu V11.1
=====

OS Install Disk: Yes

Hostname: eppve

DHCP
eth0 Address: 192.168.31.29
eth0 Netmask: 255.255.255.0
eth0 Gateway: 192.168.31.1
eth0 MacAddr: 00:09:da:e8:60:56

EPS Admin: https://192.168.31.29:1111
PVE Admin: https://192.168.31.29:8006
PBS Admin: https://192.168.31.29:8007

=====

2) IP Configuration
3) Changing Hostname
4) Format Disk
6) Changing root Password
7) Reboot
8) Shutdown
9) Logout

p) Ping

Press <Enter> to refresh

You Choice is:
```

ip

2)IP Configuration (ip)

192.168.0.100 255.255.255.0 192.168.0.254

192.168.31.29 255.255.255.0 192.168.31.1

```
=====
EPower AIOT SysMenu V11.1
=====

OS Install Disk: Yes

Hostname: eppve

DHCP
eth0 Address:
eth0 Netmask:
eth0 Gateway:

EPS Admin: https://:1111
PVE Admin: https://:8006
PBS Admin: https://:8007

=====

2) IP Configuration
3) Changing Hostname
4) Format Disk
6) Changing root Password
7) Reboot
8) Shutdown
9) Logout

i) Install To Disk
p) Ping

Press <Enter> to refresh

You Choice is:

2
ip netmask gateway
192.168.0.100 255.255.255.0 192.168.0.254

192.168.0.11 255.255.255.0 192.168.0.254
```

Enter

7 ip

```
=====
EPower Server SysMenu V11.1
=====

OS Install Disk: Yes

Hostname: eppve

DHCP
eth0 Address: 192.168.31.29
eth0 Netmask: 255.255.255.0
eth0 Gateway: 192.168.31.1
eth0 MacAddr: 00:09:da:e8:60:56

EPS Admin: https://192.168.31.29:1111
PVE Admin: https://192.168.31.29:8006
PBS Admin: https://192.168.31.29:8007

=====

2) IP Configuration
3) Changing Hostname
4) Format Disk
6) Changing root Password
7) Reboot
8) Shutdown
9) Logout

p) Ping

Press <Enter> to refresh

You Choice is:
```

ip http://192.168.31.29:1111 Epower

Username : admin

Password : Epower123



————— Login —————

Username

Password

Log In



Revision #9

Created 5 January 2023 02:03:32 by Epower

Updated 13 January 2023 07:12:17 by Epower